Practical Pharmacognosy


3rd. Stage 1st semester

Dr. Zahraa Shubber Lab.5





Volatile Oils

- They are odorous principles found in various plant parts.
- Because they **evaporate** when exposed to the air at room temperatures, they are called **volatile oils**; they are also called essential or ethereal oils.
- Volatile oils are colorless as a rule, particularly when they are **fresh**, but on long standing they may **oxidize** and resinify, thus **darkening** in color, to prevent this darkening, they should be:
- stored in a cool
- dry place in tightly Stoppard
- preferably full
- **amber glass containers.**



- As a rule, volatile oils are **immiscible with water**, but they are sufficiently soluble to impart their odor to water.
- They are soluble in **ether**, **alcohol** and **most organic** solvents.
- Many volatile oils consist largely of **terpenes** (terpenes are natural products whose structures may be divided into **isoprene units**). Another major group of volatile oil constituents are the **phenylpropanoids**. (These compounds contain the C6 phenyl ring with an attached C3 propane side chain).





Isoprene unit

Phenylpropanoids

Generally:

volatile oils and volatile oil-containing drugs are divided in to the following classes:

- 1. Hydrocarbons.
- 2. Alcohols.
- 3. Aldehydes.
- 4. Ketones.
- 5.Phenols.
- 6.Phenolic ethers.
- 7.Oxides.
- 8.Esters.



- Essential oils are derived from various sections of plants:
- •Leaves- Rosemary, Basil, Eucalyptus.
- •Flowers- Rose, Lavender, Clove.
- •Seeds- Almonds, Anise, cumin.
- •Bark- Cinnamon.
- •Rhizome- Ginger.









Pharmacological Uses of Volatile Oils:

- •Carminative as for Rosemary oil.
- Antitussive as for Eucalyptus.
- •Antiseptic as Clove oil.
- •Aromatherapy, alternative medicine as Lavender Oil.



Isolation and Identification of the Volatile Oils:

Aim: Determination of the volatile content of crude drugs by steam distillation method.

Equipment: Clevenger type as an apparatus.



Clevenger Apparatus
(Oil heavier than Water)



Clevenger Apparatus
(Oil lighter than water)

Procedure:

- 1) Weigh out 20 gm of the plant material (coarse powder) and place into a distilling flask; add few pieces of porous earthenware.
- 2)Add 200 ml distilled water to the flask and shake well. Add another 200ml of water by rinsing the neck of the flask.
- 3)Connect the distilling flask with the still head of the apparatus. By the means of the pipette or washing bottle, fill the receiver with water until over flows.
- 4)Connect the condenser of the apparatus with the cooling water (from the tap).
- 5)Heat the distilling flask until the boiling starts. Record the time of the beginning of distillation, and continue the distillation for one hour.
- 6)Switch off heating. Allow the graduated receiver to cool. Read off the volume of the volatile oil (count all small divisions in the receiver of the layer of oil).
- 7) Calculate the %v/w of the volatile oil content of drug.

Identification of Volatile Oils By Chromatography:

By the use of thin layer chromatography (T.L.C).

- ■The stationary phase = Silica gel G.
- ■The mobile phase = Chloroform: Benzene (3:1).
- ■The standard compound = Peppermint Oil.
- The spray reagent = Vanilline _Sulphuric acid / Ethanol (10%v/v).
- Mechanism of separation = Adsorption.
- Developing = Ascending.

Procedure:

- 1)Prepare 100ml of mobile phase, and place it in the glass tank.
- 2)Cover the tank with glass lid and allow standing for 45 minutes before use.
- 3)Apply the sample spot and the standard spot on the silica gel plates, on the base line.
- 4)Put the silica gel plate in the glass tank and allow the mobile phase to rise to about two-third the plate.
- 5)Remove the plate from the tank, and allow drying and then detecting the spots by the use of the spray reagent and heat the plates at 120°C until the spot's color intensity is reached in the oven. Detect the spot and calculate the Rf value.

Thank you

